



Tanium™ End-User Notifications User Guide

Version 1.15.54

July 27, 2023

The information in this document is subject to change without notice. Further, the information provided in this document is provided “as is” and is believed to be accurate, but is presented without any warranty of any kind, express or implied, except as provided in Tanium’s customer sales terms and conditions. Unless so otherwise provided, Tanium assumes no liability whatsoever, and in no event shall Tanium or its suppliers be liable for any indirect, special, consequential, or incidental damages, including without limitation, lost profits or loss or damage to data arising out of the use or inability to use this document, even if Tanium Inc. has been advised of the possibility of such damages.

Any IP addresses used in this document are not intended to be actual addresses. Any examples, command display output, network topology diagrams, and other figures included in this document are shown for illustrative purposes only. Any use of actual IP addresses in illustrative content is unintentional and coincidental.

Please visit <https://docs.tanium.com> for the most current Tanium product documentation.

This documentation may provide access to or information about content, products (including hardware and software), and services provided by third parties (“Third Party Items”). With respect to such Third Party Items, Tanium Inc. and its affiliates (i) are not responsible for such items, and expressly disclaim all warranties and liability of any kind related to such Third Party Items and (ii) will not be responsible for any loss, costs, or damages incurred due to your access to or use of such Third Party Items unless expressly set forth otherwise in an applicable agreement between you and Tanium.

Further, this documentation does not require or contemplate the use of or combination with Tanium products with any particular Third Party Items and neither Tanium nor its affiliates shall have any responsibility for any infringement of intellectual property rights caused by any such combination. You, and not Tanium, are responsible for determining that any combination of Third Party Items with Tanium products is appropriate and will not cause infringement of any third party intellectual property rights.

Tanium is committed to the highest accessibility standards for our products. To date, Tanium has focused on compliance with U.S. Federal regulations - specifically Section 508 of the Rehabilitation Act of 1998. Tanium has conducted 3rd party accessibility assessments over the course of product development for many years and has most recently completed certification against the WCAG 2.1 / VPAT 2.3 standards for all major product modules in summer 2021. In the recent testing the Tanium Console UI achieved supports or partially supports for all applicable WCAG 2.1 criteria. Tanium can make available any VPAT reports on a module-by-module basis as part of a larger solution planning process for any customer or prospect.

As new products and features are continuously delivered, Tanium will conduct testing to identify potential gaps in compliance with accessibility guidelines. Tanium is committed to making best efforts to address any gaps quickly, as is feasible, given the severity of the issue and scope of the changes. These objectives are factored into the ongoing delivery schedule of features and releases with our existing resources.

Tanium welcomes customer input on making solutions accessible based on your Tanium modules and assistive technology requirements. Accessibility requirements are important to the Tanium customer community and we are committed to prioritizing these compliance efforts as part of our overall product roadmap. Tanium maintains transparency on our progress and milestones and welcomes any further questions or discussion around this work. Contact your sales representative, email Tanium Support at support@tanium.com, or email accessibility@tanium.com to make further inquiries.

Tanium is a trademark of Tanium, Inc. in the U.S. and other countries. Third-party trademarks mentioned are the property of their respective owners.

© 2023 Tanium Inc. All rights reserved.

Table of contents

- End-User Notifications overview** 5
 - End-User Notifications 5
 - End-User Self Service 5
 - Interoperability with other Tanium products 5
 - Deploy 5
 - Enforce 5
 - Engage 5
 - Patch 6
- Getting started** 7
 - Step 1: Install and configure Tanium End-User Notifications 7
 - Step 2: Configure endpoint restart notifications for Deploy or Patch deployments 7
 - Step 3: Configure notifications for Enforce FileVault or BitLocker policies 7
 - Step 4: Create Engage surveys for end users 7
 - Step 5: Customize the end-user interface to use with Deploy, Patch, or Engage 7
- End-User Notifications requirements** 8
 - Core platform dependencies 8
 - Computer group dependencies 8
 - Solution dependencies 8
 - Tanium recommended installation 8
 - Import specific solutions 9
 - Required dependencies 9
 - Feature-specific dependencies 9
 - Tanium™ Module Server 9
 - Endpoints 9
 - Host and network security requirements 10
 - Ports 10
 - Security exclusions 10

User role requirements	13
Installing End-User Notifications	16
Before you begin	16
Import End-User Notifications with default settings	16
Import End-User Notifications with custom settings	17
Manage solution dependencies	17
Upgrade End-User Notifications	17
Verify End-User Notifications version	17
Configuring End-User Notifications	19
Install and configure Tanium Endpoint Configuration	19
Manage solution configurations with Tanium Endpoint Configuration	19
Configure End-User Notifications	20
Configure the End-User Notifications action group	20
Customize the End-User Self Service Client	20
Set up End-User Notifications users	20
Initialize endpoints	21
Customizing the End-User Self Service interface	22
Create a configuration	22
Prioritize configurations	23
View, edit, or delete configurations	23
Troubleshooting End-User Notifications	24
Collect logs	24
Upgrading to End-User Notifications 1.15	24
Perform monthly maintenance	24
Problem: End user notifications are not displayed or endpoints have errors	25
Problem: End-User Notifications tools missing on endpoints	25
Uninstall End-User Notifications	25
Remove End-User Notifications tools from endpoints	26
Contact Tanium Support	27

End-User Notifications overview

End-User Notifications is a shared service that is used by other Tanium products, such as Tanium™ Deploy, Tanium™ Patch, Tanium™ Enforce, and Tanium™ Engage, to notify users about system actions. It is also used by Deploy, Patch, and Engage for self service capabilities.

End-User Notifications

When you use End-User Notifications with other solutions, you can create notification messages to notify the user of system actions or user requirements.

End-User Self Service

When you use End-User Notifications with Deploy, Patch, and Engage, you can configure the Self Service Client application for Windows endpoints. With the Self Service Client application, you can publish software to endpoints so that users can install software on their own without the need for IT to install for them. For more information, see [Customizing the End-User Self Service interface on page 22](#).

Interoperability with other Tanium products

End-User Notifications works with other Tanium products to provide additional features.

Deploy

End-User Notifications is used by Deploy to notify users about deployments to Windows and macOS endpoints, and to configure End-User Self Service capabilities to Windows endpoints. You can create a notification message with your deployment to notify the user that the system is about to begin a deployment, has completed a deployment, and if postponements are enabled, to give the user the option to postpone the deployment or restart now. For more information, see [Tanium Deploy User Guide: Using the Self Service Client application](#).

Enforce

End-User Notifications is used by Enforce to instruct users to enable encryption, and to notify users before a restart. You can create a notification message in the FileVault policy that displays either at log out or during the next log in. Users can dismiss the message multiple times if the FileVault policy allows it. For more information, see [Tanium Enforce User Guide: Create a FileVault policy](#). You can also create a notification message that displays to the user after a BitLocker policy is enforced. The message notifies users before the computer is restarted to prepare their drives for encryption. For more information, see [Tanium Enforce User Guide: Create a BitLocker policy](#).

Engage

End-User Notifications is used by Engage to send surveys to endpoint users to collect qualitative feedback and deploy remediations to correct problems on the endpoints. For more information, see [Tanium Engage User Guide: Creating surveys](#).

Patch

End-User Notifications is used by Patch to notify users about deployments to Windows endpoints and to configure End-User Self Service capabilities to Windows endpoints. You can create a notification message with your deployment to notify the user that the system is about to begin a deployment, has completed a deployment, and if postponements are enabled, to give the user the option to postpone the deployment or restart now. For more information, see [Tanium Patch User Guide: Managing End-User Self Service](#).

Getting started

Step 1: Install and configure Tanium End-User Notifications

Install and configure Tanium End-User Notifications.

For more information, see [Installing End-User Notifications on page 16](#).

Step 2: Configure endpoint restart notifications for Deploy or Patch deployments

Configure endpoint restart notifications for Deploy or Patch deployments.

For more information, see [Tanium Deploy User Guide: Deploying packages and bundles](#) or [Tanium Patch User Guide: Deploying patches](#).

Step 3: Configure notifications for Enforce FileVault or BitLocker policies

Configure notifications for Enforce FileVault or BitLocker policies.

For more information, see [Tanium Enforce User Guide: Create a FileVault policy](#) or [Tanium Enforce User Guide: Create a BitLocker policy](#).

Step 4: Create Engage surveys for end users

Create Engage surveys for end users to collect qualitative feedback and deploy remediations to correct problems on the endpoints.

For more information, see [Tanium Engage User Guide: Creating surveys](#).

Step 5: Customize the end-user interface to use with Deploy, Patch, or Engage

Customize the end-user interface to use with Deploy, Patch, or Engage.

For more information, see [Customizing the End-User Self Service interface on page 22](#).

End-User Notifications requirements

Review the requirements before you install and use End-User Notifications.

Core platform dependencies

Make sure that your environment meets the following requirements:

- Tanium license that includes End-User Notifications
- **Tanium™ Core Platform servers:** 7.4.3.1204 or later
- **Tanium™ Client:** Any supported version of Tanium Client. For the Tanium Client versions supported for each OS, see [Tanium Client Management User Guide: Client version and host system requirements](#).

If you use a client version that is not listed, certain product features might not be available, or stability issues can occur that can only be resolved by upgrading to one of the listed client versions.

Computer group dependencies

When you first sign in to the Tanium Console after a fresh installation of Tanium Server, the server automatically imports the **ALL Computers** computer group, which End-User Notifications requires.

For earlier versions of the Tanium Server, or after upgrading from an earlier version, you must manually create the computer groups. See [Tanium Console User Guide: Create a computer group](#).

Solution dependencies

Other Tanium solutions are required for End-User Notifications to function (required dependencies) or for specific End-User Notifications features to work (feature-specific dependencies). The installation method that you select determines if the Tanium Server automatically imports dependencies or if you must manually import them.



Some End-User Notifications dependencies have their own dependencies, which you can see by clicking the links in the lists of [Required dependencies on page 9](#) and [Feature-specific dependencies on page 9](#). Note that the links open the user guides for the latest version of each solution, not necessarily the minimum version that End-User Notifications requires.

Tanium recommended installation

If you select **Tanium Recommended Installation** when you import End-User Notifications, the Tanium Server automatically imports all your licensed solutions at the same time. See [Tanium Console User Guide: Import all modules and services](#).

Import specific solutions

If you select only End-User Notifications to import and are using Tanium Core Platform 7.5.2.3531 or later with Tanium Console 3.0.72 or later, the Tanium Server automatically imports the latest available versions of any required dependencies that are missing. If some required dependencies are already imported but their versions are earlier than the minimum required for End-User Notifications, the server automatically updates those dependencies to the latest available versions.

If you select only End-User Notifications to import and you are using Tanium Core Platform 7.5.2.3503 or earlier with Tanium Console 3.0.64 or earlier, you must manually import or update required dependencies. See [Tanium Console User Guide: Import, re-import, or update specific solutions](#).

Required dependencies

End-User Notifications has the following required dependencies at the specified minimum versions:

- Tanium [Endpoint Configuration](#) 1.2 or later
- Tanium™ System User Service 1.0.77 or later
- Tanium™ RDB Service 1.2.214 or later
- Tanium [Trends](#) 3.9.343 or later

Feature-specific dependencies

If you select only End-User Notifications to import, you must manually import or update its feature-specific dependencies regardless of the Tanium Console or Tanium Core Platform versions. End-User Notifications has the following feature-specific dependencies at the specified minimum versions:


- Tanium [Deploy](#) 2.11 or later for end-user notifications or end-user self service
- Tanium [Enforce](#) 1.5 or later for end-user notifications for BitLocker or FileVault policies
- Tanium [Engage](#) 1.0.96 or later for end-user notifications and end-user self service
- (macOS) Tanium [Patch](#) 3.6 or later for end-user notifications
- (Windows) Tanium [Patch](#) 3.12 or later for end-user notifications or end-user self service
- Tanium [Reporting](#) 1.12 or later. Creates charts on the **Overview** page. If this version is not installed, Trends creates the charts.

Tanium™ Module Server

End-User Notifications is installed and runs as a service on the Module Server host computer. The impact on the Module Server is minimal and depends on usage.

Endpoints

End-User Notifications supports the following client operating systems:

Operating System	Version	Notes
Windows Server	Windows Server 2008 R2 Service Pack 1 or later	<ul style="list-style-type: none"> Windows Server Core not supported for End-User Notifications functionality. Windows Server 2008 R2 Service Pack 1 requires Microsoft KB2758857. Windows Server 2012 R2 requires Microsoft KB2919394 or KB2919355 for End-User Self Service functionality.
Windows Workstation	Windows 7 Service Pack 1 or later	<ul style="list-style-type: none"> Windows 7 Service Pack 1 requires Microsoft KB2758857. Windows 8.1 requires Microsoft KB2919394 or KB2919355 for End-User Self Service functionality.
macOS	<ul style="list-style-type: none"> macOS 13 Ventura macOS 12 Monterey macOS 11 Big Sur macOS 10.15 Catalina macOS 10.14.6 Mojave macOS 10.13.6 High Sierra 	<div style="border: 1px solid #ccc; padding: 5px; display: flex; align-items: center;">  <p>End-User Self Service is not available on macOS operating systems.</p> </div>

Host and network security requirements

Specific ports and processes are needed to run End-User Notifications.

Ports

The following ports are required for End-User Notifications communication.

Source	Destination	Port	Protocol	Purpose
Module Server	Module Server (loopback)	17476	TCP	Internal purposes; not externally accessible



BEST PRACTICE

Configure firewall policies to open ports for Tanium traffic with TCP-based rules instead of application identity-based rules. For example, on a Palo Alto Networks firewall, configure the rules with service objects or service groups instead of application objects or application groups.

Security exclusions

If security software is in use in the environment to monitor and block unknown host system processes, Tanium recommends that a security administrator create exclusions to allow the Tanium processes to run without interference. The configuration of these exclusions varies depending on AV software. For a list of all security exclusions to define across Tanium, see [Tanium Core Platform](#)

[Deployment Reference Guide: Host system security exclusions.](#)

End-User Notifications security exclusions

Target Device	Notes	Exclusion Type	Exclusion
Module Server	Required when Endpoint Configuration is installed	Process	<Module Server>\temp\endpoint-configuration-service\taniumEndpointConfigService.exe
		Process	<Module Server>\services\end-user-notifications-service\node.exe
		Process	<Module Server>\services\twsm-v1\twsm.exe

End-User Notifications security exclusions (continued)

Target Device	Notes	Exclusion Type	Exclusion
Windows endpoints	7.2.x clients	Process	<Tanium Client>\Python27\TPython.exe
	7.4.x clients	Process	<Tanium Client>\Python38\TPython.exe
	64-bit OS versions	Process	%programfiles(x86)%\Tanium\Tanium End User Notification Tools\UserSessionProxy.exe
	32-bit OS versions	Process	%programfiles%\Tanium\Tanium End User Notification Tools\UserSessionProxy.exe
	64-bit OS versions	Process	%programfiles(x86)%\Tanium\Tanium End User Notification Tools\bin\end-user-notifications.exe
	32-bit OS versions	Process	%programfiles%\Tanium\Tanium End User Notification Tools\bin\end-user-notifications.exe
	exclude from on-access or real-time scans (64-bit OS versions)	Folder	%programfiles(x86)%\Tanium\Tanium End User Notification Tools
	exclude from on-access or real-time scans (32-bit OS versions)	Folder	%programfiles%\Tanium\Tanium End User Notification Tools
		Folder	%programdata%\Tanium
	64-bit OS versions	Folder	%programfiles(x86)%\Tanium\Tanium Client\Tools\EndUserNotifications\scripts
	64-bit OS versions	File	%programfiles(x86)%\Tanium\Tanium Client\Tools\EndUserNotifications\scripts\config.vbs
	64-bit OS versions	File	%programfiles(x86)%\Tanium\Tanium Client\Tools\EndUserNotifications\scripts\remove-end-user-notifications.vbs

End-User Notifications security exclusions (continued)

Target Device	Notes	Exclusion Type	Exclusion
macOS endpoints	7.2.x clients	Process	<Tanium Client>/python27/bin/pybin
	7.4.x clients	Process	<Tanium Client>/python38/bin/pybin
		Process	/Library/Tanium/EndUserNotifications/bin/end-user-notifications.app
		Folder	/Library/Tanium/EndUserNotifications

User role requirements

The following tables list the role permissions required to use End-User Notifications. To review a summary of the predefined roles, see [Set up End-User Notifications users on page 20](#).















Do not assign the **End-User Notifications Service Account** and **End-User Notifications Service Account - All Content Sets** roles to users. These roles are for internal purposes only.

For more information about role permissions and associated content sets, see [Tanium Core Platform User Guide: Managing RBAC](#).

End-User Notifications user role permissions

Permission	End-User Notifications Administrator ^{1,2,3}	End-User Notifications Endpoint Configuration Approver ^{1,2,3}	End-User Notifications Operator ^{1,2,3}	End-User Notifications Read Only User ^{1,2,3}
End-User Notifications Endpoint Configuration APPROVE: Approve End-User Notifications items for Endpoint Configuration REGISTER: Access to register with Endpoint Configuration	 REGISTER	 APPROVE		
End-User Notifications Module Read and write access to the End-User Notifications shared service	 READ WRITE	 READ	 READ	 READ

End-User Notifications user role permissions (continued)













Permission	End-User Notifications Administrator ^{1,2,3}	End-User Notifications Endpoint Configuration Approver ^{1,2,3}	End-User Notifications Operator ^{1,2,3}	End-User Notifications Read Only User ^{1,2,3}
End-User Notifications Operator Module Write access to a subset of the End-User Notifications shared service	 WRITE		 WRITE	
End-User Notifications Use API Access to the End-User Notifications API	 EXECUTE	 EXECUTE	 EXECUTE	 EXECUTE
Endusertnotifications View the End-User Notifications shared service	 SHOW	 SHOW	 SHOW	 SHOW

¹ This role provides module permissions for Tanium Endpoint Configuration. You can view which Endpoint Configuration permissions are granted to this role in the Tanium Console. For more information, see [Tanium Endpoint Configuration User Guide: User role requirements](#).

² This role provides module permissions for Tanium Interact. You can view which Interact permissions are granted to this role in the Tanium Console. For more information, see [Tanium Interact User Guide: Tanium Data Service permissions](#).

³ This role provides module permissions for Tanium Trends. You can view which Trends permissions are granted to this role in the Tanium Console. For more information, see [Tanium Trends User Guide: User role requirements](#).

Provided End-User Notifications administration and platform content permissions

Permission	Permission Type	End-User Notifications Administrator ^{1,2}	End-User Notifications Endpoint Configuration Approver ²	End-User Notifications Operator ²	End-User Notifications Read Only User ²
Computer Group	Administration	 READ	 READ	 READ	 READ
User	Administration	 READ		 READ	
User Group	Administration	 READ	 READ	 READ	 READ

Provided End-User Notifications administration and platform content permissions (continued)

Permission	Permission Type	End-User Notifications Administrator ^{1,2}	End-User Notifications Endpoint Configuration Approver ²	End-User Notifications Operator ²	End-User Notifications Read Only User ²
Action	Platform Content	✔ WRITE	✘	✔ WRITE	✘
Approve Action	Platform Content	✔ SPECIAL	✘	✔ SPECIAL	✘
Own Action	Platform Content	✔ READ	✘	✔ READ	✘
Package	Platform Content	✔ READ WRITE	✘	✔ READ WRITE	✘
Plugin	Platform Content	✔ READ EXECUTE	✔ READ EXECUTE	✔ READ EXECUTE	✔ READ EXECUTE
Saved Question	Platform Content	✔ READ WRITE	✘	✔ READ WRITE	✘
Sensor	Platform Content	✔ READ	✔ READ	✔ READ	✔ READ

To view which content set permissions are granted to a role, see [Tanium Console User Guide: View effective role permissions](#).

¹ This role provides content set permissions for Tanium Endpoint Configuration. You can view which Endpoint Configuration content sets are granted to this role in the Tanium Console. For more information, see [Tanium Endpoint Configuration User Guide: User role requirements](#).

² This role provides module permissions for Tanium Trends. You can view which Trends permissions are granted to this role in the Tanium Console. For more information, see [Tanium Trends User Guide: User role requirements](#).

For more information and descriptions of content sets and permissions, see [Tanium Core Platform User Guide: Users and user groups](#).

Installing End-User Notifications

Use the **Solutions** page to install End-User Notifications and choose either automatic or manual configuration:

- **Automatic configuration with default settings** (Tanium Core Platform 7.4.2 or later only): End-User Notifications is installed with any required dependencies and other selected products. After installation, the Tanium Server automatically configures the recommended default settings. This option is the best practice for most deployments. For more information about the automatic configuration for End-User Notifications, see [Import End-User Notifications with default settings on page 16](#).
- **Manual configuration with custom settings**: After installing End-User Notifications, you must manually configure required settings. Select this option only if End-User Notifications requires settings that differ from the recommended default settings. For more information, see [Import End-User Notifications with custom settings on page 17](#).

Before you begin

- Read the [release notes](#).
- Review the [End-User Notifications requirements on page 8](#).
- If you are upgrading from a previous version, see [Upgrade End-User Notifications on page 17](#).

Import End-User Notifications with default settings

(Tanium Core Platform 7.4.5 or later only) You can set the End-User Notifications action group to target the **No Computers** filter group by enabling restricted targeting before importing End-User Notifications. This option enables you to control tools deployment through scheduled actions that are created during the import and that target the Tanium End-User Notifications action group. For example, you might want to test tools on a subset of endpoints before deploying the tools to all endpoints. In this case, you can manually deploy the tools to an action group that you configured to target only the subset. To configure an action group, see [Tanium Console User Guide: Managing action groups](#). To enable or disable restricted targeting, see [Tanium Console User Guide: Dependencies, default settings, and tools deployment](#).

When you import End-User Notifications with automatic configuration, the following default settings are configured:

Setting	Default value
Action group	<ul style="list-style-type: none">• Restricted targeting disabled (default): <code>All Computers</code> computer group• Restricted targeting enabled: <code>No Computers</code> computer group
End-User Notifications configurations	<ul style="list-style-type: none">• A default End-User Notifications configuration is created.• The End-User Notifications tools are distributed to endpoints.

To import End-User Notifications and configure default settings, be sure to select the **Apply All Tanium recommended configurations** check box while performing the steps in [Tanium Console User Guide: Import all modules and services](#). After the import, verify that the correct version is installed. For more information, see [Verify End-User Notifications version on page 17](#).

Import End-User Notifications with custom settings

To import End-User Notifications without automatically configuring default settings, be sure to clear the **Apply All Tanium recommended configurations** check box while performing the steps in [Tanium Console User Guide: Import, re-import, or update specific solutions](#). After the import, verify that the correct version is installed. For more information, see [Verify End-User Notifications version on page 17](#).

To configure the End-User Notifications action group, see [Configure the End-User Notifications action group on page 20](#).

To customize notifications, see [Customize the End-User Self Service Client on page 20](#).

Manage solution dependencies

When you start the End-User Notifications workbench for the first time, the Tanium Server checks whether all the Tanium modules and shared services (solutions) that are required for End-User Notifications are installed at the required versions. The End-User Notifications workbench cannot load unless all required dependencies are installed. If you selected **Tanium Recommended Installation** when you imported End-User Notifications, the Tanium Server automatically imported all your licensed solutions at the same time. Otherwise, if you manually imported End-User Notifications and did not import all its dependencies, Tanium Console displays a banner that lists the dependencies and the required versions. See [Solution dependencies](#).

1. Install the dependencies as described in [Tanium Console User Guide: Import, re-import, or update specific solutions](#).
2. From the Main menu, go to **Shared Services > End-User Notifications** to open the End-User Notifications **Overview** page and verify that the Console no longer displays a banner to list missing dependencies.

Upgrade End-User Notifications




In End-User Notifications 1.15, the steps required to configure the service account are no longer necessary due to the adoption of the System User Service, which performs these tasks automatically. Additionally, the End-User Notifications database is migrated to RDB in this release. Consequently, after upgrading to End-User Notifications 1.15, it might take time for the database migration to complete and for RBAC privileges and other updates to sync properly. This could lead to issues and error messages when you first query the Tanium Console. These issues should resolve on their own after a few minutes, but could take up to an hour or longer depending on system resources and the amount of data to migrate.

For the steps to upgrade End-User Notifications, see [Tanium Console User Guide: Import all modules and services](#). After the upgrade, verify that the correct version is installed. For more information, see [Verify End-User Notifications version on page 17](#).

Verify End-User Notifications version

After you import or upgrade End-User Notifications, verify that the correct version is installed:

1. Refresh your browser.
2. From the Main menu, go to **Shared Services > End-User Notifications**.
3. To display version information, click Info .

Configuring End-User Notifications

If you did not install End-User Notifications with the **Apply All Tanium recommended configurations** option, you must enable and configure certain features.

Install and configure Tanium Endpoint Configuration

Manage solution configurations with Tanium Endpoint Configuration


Tanium Endpoint Configuration delivers configuration information and required tools for Tanium Solutions to endpoints. Endpoint Configuration consolidates the configuration actions that traditionally accompany additional Tanium functionality and eliminates the potential for timing errors that occur between when a solution configuration is made and the time that configuration reaches an endpoint. Managing configuration in this way greatly reduces the time to install, configure, and use Tanium functionality, and improves the flexibility to target specific configurations to groups of endpoints.



For information about installing Endpoint Configuration, see [Tanium Endpoint Configuration User Guide: Installing Endpoint Configuration](#).

Optionally, you can use Endpoint Configuration to require approval of configuration changes. When configuration approvals are enabled, Endpoint Configuration does not deploy a configuration change to endpoints until a user with approval permission approves the change. For information about the roles and permissions that are required to approve configuration changes for End-User Notifications, see [User role requirements on page 13](#). For more information about enabling and using configuration approvals in Endpoint Configuration, see [Tanium Endpoint Configuration User Guide: Managing approvals](#).



For solutions to perform configuration changes or tool deployment through Endpoint Configuration on endpoints with action locks turned on, you must enable the **Manifest Package Ignore Action Lock** and **Deploy Client Configuration and Support Package Ignore Action Lock** settings. To access these settings, from the Endpoint Configuration **Overview** page, click Settings  and select **Global**. For more information about action locks, see [Tanium Console User Guide: Managing action locks](#).

For more information about Endpoint Configuration, see [Tanium Endpoint Configuration User Guide](#).

If you enabled configuration approvals, you must approve creating, editing, and deleting End-User Notifications configurations in Endpoint Configuration before they deploy to endpoints.

Configure End-User Notifications

Configure the End-User Notifications action group

Importing the End-User Notifications module automatically creates an action group to target specific endpoints. If you did not use automatic configuration or you enabled restricted targeting when you imported End-User Notifications, the action group targets **No Computers**.

If you used automatic configuration and restricted targeting was disabled when you imported End-User Notifications, configuring the End-User Notifications action group is optional.

Select the computer groups to include in the End-User Notifications action group.



BEST PRACTICE

Clear the selection for **No Computers** and make sure that all operating systems that are supported by End-User Notifications are included in the End-User Notifications action group.

1. From the Main menu, go to **Administration > Actions > Action Groups**.
2. Click **Tanium End-User Notifications**.
3. Select the computer groups that you want to include in the action group and click **Save**.
If you select multiple computer groups, choose an operator (AND or OR) to combine the groups.

Customize the End-User Self Service Client

Add a company logo and relevant information to personalize the End-User Self-Service experience.

You must create at least one End-User Notifications configuration. For more information about creating a configuration, see [Create a configuration on page 22](#).

Set up End-User Notifications users

You can use the following set of predefined user roles to set up End-User Notifications users.

To review specific permissions for each role, see [User role requirements on page 13](#).



IMPORTANT

On installation, End-User Notifications creates a **End-User Notifications** user to automatically manage the End-User Notifications service account. Do not edit or delete the **End-User Notifications** user.

For more information about assigning user roles, see [Tanium Core Platform User Guide: Manage role assignments for a user](#).

End-User Notifications Administrator

Assign the **End-User Notifications Administrator** role to users who manage the configuration and deployment of End-User Notifications functionality to endpoints.

End-User Notifications Endpoint Configuration Approver

Assign the **End-User Notifications Endpoint Configuration Approver** role to a user who approves or rejects End-User Notifications configuration items in Tanium Endpoint Configuration. This role can approve, reject, or dismiss End-User Notifications configuration changes.

End-User Notifications Endpoint Configuration Operator

Assign the **End-User Notifications Operator** role to users who manage most configurations and deployment of End-User Notifications functionality to endpoints.

End-User Notifications Endpoint Configuration Read Only User


Assign the **End-User Notifications Read Only User** role to users who need visibility into End-User Notifications settings but do not need rights to update them.



Do not assign the **End-User Notifications Service Account** and **End-User Notifications Service Account - All Content Sets** roles to users. These roles are for internal purposes only.

Initialize endpoints

End-User Notifications installs a set of tools on each endpoint that you have targeted. Initializing endpoints configures the End-User Notifications Tools to be installed on any compatible endpoint in the End-User Notifications action group. You must complete this procedure any time the action group is changed.

1. On the End-User Notifications **Overview** page, click Help , and then click **Support**.
2. Click **Initialize Endpoints** and confirm your action.



After deploying the tools for the first time, endpoints can take up to four hours to display status.

Customizing the End-User Self Service interface

To customize the End-User Self Service interface to use with Deploy, Patch, or Engage on Windows endpoints, create additional End-User Notifications configurations. Each configuration defines settings, rules, or parameters that apply to one or more computer groups.

If you use End-User Self Service for both Deploy, Patch, or Engage deployments, only one End-User Self Service application is distributed to each endpoint.

Create a configuration

1. From the End-User Notifications menu, click **Configurations** and then click **Create Configuration**.
2. Provide a name and optional description.
3. Select targeting options.



Only one configuration can apply to an endpoint.

NOTE

4. Configure the application details.
 - a. Specify a name for the application shortcut on endpoints.
 - b. Specify a URL or email address where users can find support.
 - c. Upload a logo file to display in the self-service dashboard on endpoints.
 - d. Upload an icon file that will be used for the application shortcut on endpoints.
5. (Optional) Select **Enable End-User Self Service**.
 - a. Provide a header title and welcome message to display in the self-service dashboard on endpoints.
 - b. Select installation options.
6. (Optional) Select **Enable Additional Languages**.
 - a. Select a language and provide a translated application name, header title, and welcome message.
 - b. (Optional) Click **Add Language** to add more languages.



By default, the Self Service Client application displays content in the system language on the endpoints. If you enable additional languages, the user can select other languages to display.

NOTE

7. Click **Submit**.

After you customize the End-User Self Service interface, complete the following applicable tasks:

- Create a self service profile in Deploy. For more information, see [Tanium Deploy User Guide: Using the Self Service Client application](#).
- Create a self service deployment in Patch. For more information, see [Tanium Patch User Guide: Managing End-User Self Service](#).

Prioritize configurations

If you have more than one configuration, you can prioritize them. Endpoints targeted with more than one configuration use the settings from the highest priority configuration.

1. From the End-User Notifications menu, click **Configurations** and then click **Prioritize**.
2. Drag and drop a configuration to reprioritize it. End-User Notifications automatically adjusts the priority numbers for the other configurations and reorders the list by priority.
3. Click **Confirm**.

View, edit, or delete configurations

To view configurations, click **Configurations** from the End-User Notifications menu. You can also view them from the **Configurations** section of the End-User Notifications **Home** page.

To edit a configuration, click the name of the configuration.


To delete a configuration, select a configuration and click **Delete**.

Troubleshooting End-User Notifications

To collect and send information to Tanium for troubleshooting, collect logs and other relevant information.

Collect logs

The information is saved as a ZIP file that you can download with your browser.

1. From the End-User Notifications **Home** page, click Help , and then click **Support**.
2. Click **Collect**.
3. When **Status** indicates that the package is collected, click **Download**.
4. Contact Tanium Support to determine the best option to send the ZIP file. For more information, see [Contact Tanium Support on page 27](#).

End-User Notifications maintains logging information in the log file in the `\Program Files\Tanium\Tanium Module Server\services\end-user-notifications-files\logs` directory.

Upgrading to End-User Notifications 1.15



In End-User Notifications 1.15, the steps required to configure the service account are no longer necessary due to the adoption of the System User Service, which performs these tasks automatically. Additionally, the End-User Notifications database is migrated to RDB in this release. Consequently, after upgrading to End-User Notifications 1.15, it might take time for the database migration to complete and for RBAC privileges and other updates to sync properly. This could lead to issues and error messages when you first query the Tanium Console. These issues should resolve on their own after a few minutes, but could take up to an hour or longer depending on system resources and the amount of data to migrate.

Perform monthly maintenance

1. From the Main menu, go to **Administration > Shared Services > End-User Notifications**.
2. Scroll to the **Health** dashboard to verify whether the latest End-User Notifications tools are installed and active on all endpoints.
3. To investigate endpoints that do not have the latest tools installed, click the number above **No** or **Unsupported**. The Tanium Server issues a question that returns the computer name, operating system, IP address, tools installation status, and installed tools version.
4. To troubleshoot installation issues for End-User Notifications tools, see [Problem: End user notifications are not displayed or endpoints have errors on page 25](#).

Problem: End user notifications are not displayed or endpoints have errors

If end user notifications are not being displayed on the endpoints or the endpoints have an error (for example, their statuses are **Needs Attention** in the Deploy workbench or **Non-compliant** in the Patch workbench), consider the following steps:

1. Verify that the Tanium End-User Notifications solution is installed. For more information, see [Installing End-User Notifications on page 16](#).
2. Verify that endpoints have the end user notification tools by asking the question `End-User Notifications - Has Tools`.
3. Verify that required security exclusions for End-User Notifications are configured in any security software. For more information, see [Security exclusions on page 10](#). For assistance in ensuring exclusions have taken effect, [Contact Tanium Support on page 27](#).
4. [Uninstall the tools on the endpoint](#) and then wait up to 10 minutes for the tools to automatically reinstall.



NOTE

You can also reinstall the End-User Notifications tools with the **Endpoint Configuration - Reinstall Tool** package.

Problem: End-User Notifications tools missing on endpoints

If the End-User Notifications tools are missing on endpoints, the **Tanium End-User Notifications** action group might be missing in the Tanium Console or the endpoints might not be included in the action group.



NOTE

The **Tanium End-User Notifications** action group will not be automatically created if you imported End-User Notifications using a URL and did not use the **Apply All Tanium recommended configurations** option.

1. From the Main menu, go to **Administration > Actions > Action Groups**.
2. Confirm that the **Tanium End-User Notifications** action group has been created. If the action group is missing, create it. For instructions, see [Tanium Console User Guide: Create an action group](#).
3. Confirm that the **Tanium End-User Notifications** action group includes computer groups that include the endpoints. For instructions, see [Configure the End-User Notifications action group on page 20](#).

Uninstall End-User Notifications

1. From the Main menu, go to **Administration > Configuration > Solutions**.
2. In the **Content** section, select the **End-User Notifications** row.
3. Click **Uninstall**.

Remove End-User Notifications tools from endpoints

You can deploy an action to remove End-User Notifications tools from an endpoint or computer group. Separate actions are available for Windows and non-Windows endpoints.

1. In Interact, target the endpoints from which you want to remove the tools. For example, ask a question that targets a specific operating system:

```
Get Endpoint Configuration - Tools Status from all machines with Is Windows equals true
```

2. In the results, select the row for **End-User Notifications**, drill down as necessary, and select the targets from which you want to remove End-User Notifications tools. For more information, see [Tanium Interact User Guide: Drill Down](#).
3. Click **Deploy Action**.
4. For the **Deployment Package**, select **Endpoint Configuration - Uninstall Tool [Windows]** or **Endpoint Configuration - Uninstall Tool [Non-Windows]**, depending on the endpoints you are targeting.
5. For **Tool Name**, select **End-User Notifications**.
6. (Optional) By default, after the tools are removed they cannot be reinstalled. To allow tools to be automatically reinstalled, clear the selection for **Block reinstallation**. Re-installation occurs almost immediately.



If reinstallation is blocked, you must unblock it manually:

- To allow End-User Notifications to reinstall tools, deploy the **Endpoint Configuration - Unblock Tool [Windows]** or **Endpoint Configuration - Unblock Tool [Non-Windows]** package (depending on the targeted endpoints).
- If you reinstall tools manually, select **Unblock Tool** when you deploy the **Endpoint Configuration - Reinstall Tool [Windows]** or **Endpoint Configuration - Reinstall Tool [Non-Windows]** package.

7. (Optional) To remove all End-User Notifications databases and logs from the endpoints, clear the selection for **Soft uninstall**.



When you perform a hard uninstallation of some tools, the uninstallation also removes data that is associated with the tool from the endpoint. This data might include important historical or environmental data. If data that you want to keep is associated with the tool, make sure you perform only a soft uninstallation of the tool.

8. To also remove any tools that were dependencies of the End-User Notifications tools that are not dependencies for tools from other solutions, select **Remove unreferenced dependencies**.
9. (Optional) In the **Deployment Schedule** section, configure a schedule for the action.



If some target endpoints might be offline when you initially deploy the action, select **Recurring Deployment** and set a reissue interval.

10. Click **Show preview to continue**.
11. A results grid appears at the bottom of the page showing you the targeted endpoints for your action. If you are satisfied with the results, click **Deploy Action**.



If you have enabled Endpoint Configuration approval, tool removal must be approved in Endpoint Configuration before tools are removed from endpoints.

Contact Tanium Support

To contact Tanium Support for help, sign in to <https://support.tanium.com>.